

# **SRT-SRAE SOFTWARE DOCUMENTATION SUPER-USER**

## **16. “CAN User”**

chapter 16

**Release : 1.0**

## **REVISIONS DOCUMENT**

<i>Release</i>	<i>Author</i>	<i>Date</i>	<i>Modifications</i>
1.0	F.Charbonnel	17/09/2008	• Creation


## 16.1 CAN USER

User can define for each CAN link (CAN1 and CAN2) a set of 3 frames of 8 byte to be sent..

### 16.1.1 CONFIGURATION

User must define, for each frame, an identifier, a frequency and the content of the frame

#### 16.1.1.1 IDENTIFIERS

 If Id is 0, frame will be ignored (no emission)

##### CAN1

Map : Can1 User : Ids (3 WORDS) Hexadecimal


1	2	3
CAN1 – FRAME1 Id	CAN1 – FRAME2 Id	CAN1 – FRAME3 Id

##### CAN2

Map : Can2 User : Ids (3 WORDS) Hexadecimal

1	2	3
CAN2 – FRAME1 Id	CAN2 – FRAME2 Id	CAN2 – FRAME3 Id

#### 16.1.1.2 FREQUENCIES

 If Frequency is 0, frame will be ignored (no emission)

Allowed values are: 1, 2, 4, 5, 8, 10, 20, 25, 40, 50, 100, 125, 200, 250, 500, 1000 Hz

##### CAN1

Map: Can1 User : Frequencies (3 WORDS) decimal

1	2	3
CAN1 – FRAME1 Freq	CAN1 – FRAME2 Freq	CAN1 – FRAME3 Freq

##### CAN2

Map: Can2 User : Frequencies (3 WORDS) decimal

1	2	3
CAN2 – FRAME1 Freq	CAN2 – FRAME2 Freq	CAN2 – FRAME3 Freq

### 16.1.1.3 FRAMES CONTENT

An Adr field (DWORD) is made of :

Address : 24 bits	Size : 8 bits
Field (Hexadecimal)	Size

Field can be

1. A “real” address from SYM file. In this case, Size must be filled according to type.

Ex: Lambda into SYM file

< FD.Acq.Lambda T\_USHORT 0021004c 2 >

Map value : **21004C02**

Address : 24 bits	Size : 8 bits
21004C	2

2. An Index from CLL file. In this case, Size must be filled according to type.

Ex: Lambda into CLL file

<Lambda Volts Selected Lambda measurement 0x00000000 113\* uWord .....>

Map value : **00007100**

Address : 24 bits	Size : 8 bits
71 (113 converted to hexadecimal)	2

CAN1 frames content

Map : **CanU1.tbl USER** : Addresses (8 \* 3 WORDS)

	1	2	3	4	5	6	7	8
<b>Frame 1</b>	Adr1	Adr2	Adr3	Adr4	Adr5	Adr6	Adr7	Adr8
<b>Frame 2</b>	Adr1	Adr2	Adr3	Adr4	Adr5	Adr6	Adr7	Adr8
<b>Frame 3</b>	Adr1	Adr2	Adr3	Adr4	Adr5	Adr6	Adr7	Adr8

CAN2 frames content

Map : **CanU2.tbl USER** : Addresses (8 \* 3 WORDS)

	1	2	3	4	5	6	7	8
<b>Frame 1</b>	Adr1	Adr2	Adr3	Adr4	Adr5	Adr6	Adr7	Adr8
<b>Frame 2</b>	Adr1	Adr2	Adr3	Adr4	Adr5	Adr6	Adr7	Adr8
<b>Frame 3</b>	Adr1	Adr2	Adr3	Adr4	Adr5	Adr6	Adr7	Adr8

**Frame content is at maximum of 8 bytes.**

Frame composition is chosen by user regarding data types.

Byte: 1 byte long

Word, Sword: 2 bytes long

Float, Dword: 4 bytes long

Frame can be build by user into 8 bytes limitation. A frame can contains only one byte or any combination

Correct frames for 8 byte sample:

- 8 byte (8x1=8), 4 words (4x2=8), 2 float (2x4=8), 2 words + 1 float (2 + 2 + 4 = 8),  
1 byte, 1 dword, 1 byte, 1 word (1+4+1+2=8)

### 16.1.1.4 DIAGNOSTICS

Diagnostics are shown into StsTblUser1 for CAN1 and StsTblUser2 for CAN2.

#### StsTblUser1 or StsTblUser2 content

If one user CAN configuration is correct, corresponding value is 0.

If configuration is wrong, these word gives indication.

- If a configuration error is detected, the frame is cut before the error.
- If there is more than one error, only the **first** diagnostic is shown. Addresses are verified frame by frame

Value	Meaning	
0x01yy	0x01 : unreachable or wrong address	yy : <b>Hexadecimal</b> index of wrong field into <b>tbl USER</b> 1 to 8 (0x01 to 0x08) : first frame, 9 to 16 (0x09 to 0x10) : second frame, 17 to 24 (0x11 to 0x18) : third frame)
0x02yy	0x02 : Worng Size or Address/Size incompatibles	
0x04yy	0x04 : too much data into frame (more than 8 bytes)	

CAN1 or CAN2	Yy value							
	Adr1	Adr2	Adr3	Adr4	Adr5	Adr6	Adr7	Adr8
<b>Frame 1</b>	01	02	03	04	05	06	07	08
<b>Frame 2</b>	09	0A	0B	0C	0D	0E	0F	10
<b>Frame 3</b>	11	12	13	14	15	16	17	18